# Cal Poly Art and Design Solve Keychain issues

Written By: Matt Corippo

0	Safari wants to use the "login" keychain.
6	Please enter the keychain password.
	Password:
Details	
?	(Cancel) OK

# INTRODUCTION

### What is a Keychain on a Mac?

Keychain in Mac OS X is Apple's password management Application and management system.

A keychain can store all your passwords for applications, servers, and websites, and more.

When you connect to a network server, open an email account, or access any password-protected item that is keychain-aware, your keychain can provide the password so you don't have to type it.

You start with a single keychain, which is created automatically the first time you log in to your Mac OS X user account. Your default keychain has the same password as your login password. This keychain is unlocked automatically when you log in to Mac OS X and is referred to in Keychain Access menus as the "login" keychain.

#### When Keychain problems occur...


Keychain problems occur when a user's login password does not match their keychain password. This can be caused by using authentication methods other than the standard OS X local account system.

On Art & Design lab Macs, users log in with their Cal Poly Portal credentials. However, when a user changes their CP Portal password, Keychain does **not** recognize the change automatically. When the *new password* used to log into the machine does not match the *previously used password*, the keychain does not unlock (pass along access credentials automatically).

The user is able to log onto the machine, but applications that use the keychain system (such as Safari) will give the user an error message stating that the application wants to use the "login" keychain.

#### Follow the steps below to resolve Keychain issues.

### Step 1 — Enter your previous password



# If you don't remember your old password, you'll need to delete the

keychain.

# Open Applications > Utilities >Keychain Access.


*i* Deleting a keychain also deletes all the password data saved in that keychain.

This document was generated on 2021-12-26 02:12:55 PM (MST).

# Step 2 — Can't remember....


Home1\$	≜ ⊳	Applications	•	E Font Book	• 3	rd party utilities	₽
MacHD	Þ	Library	•	🛸 Game Center	Act	ivity Monitor	
Network	Þ	opt 📄	•	Google Chrome	🔄 Ado	be AIRtion Installer	
Remote Disc	ь	System		iBooks	Add	obe AIR Uninstaller	
		Users	Þ	Image Capture	Ado	obe Appon Manager	Þ
				@ iTunes	🚺 Add	obe Flasall Manager	
				宁 Keynote	Add	obe Installers	Þ
				& Launchpad	💿 Airf	Port Utility	
				🖷 Mail	Auc	dio MIDI Setup	
				Managed Software Center	🕹 Blu	etooth File Exchange	
				Maps	Boo	ot Camp Assistant	
				C Messages	X Col	lorSync Utility	
				L Microsoft Lync	Con	nsole	
				Microsoft Office 2011	Ø Dig	ital Color Meter	
				Mission Control	Dis Dis	k Utility	
				D Notes	M Gra	ab	
				Mumbers	阑 Gra	apher	
				7 Pages	M Key	chain Access	
				PCClient	🔊 🗭 Ma	naged Sare Update	
				25 Photo Booth	Ster Mig	gration Assistant	
				Photos	Scr	ript Editor	
				Preview	🍐 Sys	stem Information	
				Q QuickTime Player	Ter	minal	
				Reminders	🙆 Voi	ceOver Utility	
				Safari	X X11	1	
				😤 Stickies			
				Stuffit Expander			
				Symantec Solutions			
				System Preferences			
				💋 TextEdit			
				TextWrangler			
				Time Machine			
				🔀 Utilities 🕨 🕨			
				A 100			

## Step 3 — Open Keychain Access Preferences




 In Keychain Access, choose
Preferences... from the Keychain Access menu.

### Step 4



On the General tab, click the Reset
My Default Keychain button.

### Step 5



- Enter your *current* CP portal password, and click **OK**.
- That's it. Log out, and log back in to the work station, and Keychain should behave.
- If you see any prompts to enter a new Keychain, use your current CP portal password.